

# Electromagnet Calibration

Generated by Doxygen 1.8.6

Wed Jun 22 2016 22:23:06



# Contents

<b>1</b>	<b>Class Index</b>	<b>1</b>
1.1	Class List	1
<b>2</b>	<b>Class Documentation</b>	<b>3</b>
2.1	YAML::convert< Eigen::Matrix3d > Struct Template Reference	3
2.2	YAML::convert< Eigen::MatrixXd > Struct Template Reference	3
2.3	YAML::convert< Eigen::Vector3d > Struct Template Reference	3
2.4	YAML::convert< Eigen::VectorXd > Struct Template Reference	4
2.5	YAML::convert< std::vector< double > > Struct Template Reference	4
2.6	ElectromagnetCalibration Class Reference	4
2.6.1	Detailed Description	6
2.6.2	Member Enumeration Documentation	6
2.6.2.1	calibration_constraints	6
2.6.3	Constructor & Destructor Documentation	7
2.6.3.1	ElectromagnetCalibration	7
2.6.3.2	ElectromagnetCalibration	7
2.6.3.3	ElectromagnetCalibration	7
2.6.4	Member Function Documentation	7
2.6.4.1	calibrate	7
2.6.4.2	fieldAndGradientAtPoint	8
2.6.4.3	fieldAndGradientCurrentJacobian	8
2.6.4.4	fieldAtPoint	8
2.6.4.5	fieldCurrentJacobian	8
2.6.4.6	fullMagneticState	9
2.6.4.7	fullMagneticState	10
2.6.4.8	gradientAtPoint	10
2.6.4.9	gradientCurrentJacobian	10
2.6.4.10	gradientPositionJacobian	11
2.6.4.11	loadCalibration	11
2.6.4.12	offsetFieldAndGradientAtPoint	11
2.6.4.13	packForceMatrix	11

2.6.4.14	<a href="#">pointInWorkspace</a>	11
2.6.4.15	<a href="#">printStats</a>	12
2.6.4.16	<a href="#">remapGradientMatrix</a>	12
2.6.4.17	<a href="#">remapGradientVector</a>	12
2.6.4.18	<a href="#">writeCalibration</a>	12
2.7	<a href="#">MagneticMeasurement Struct Reference</a>	12
2.7.1	<a href="#">Detailed Description</a>	13
2.7.2	<a href="#">Constructor &amp; Destructor Documentation</a>	13
2.7.2.1	<a href="#">MagneticMeasurement</a>	13
2.7.2.2	<a href="#">MagneticMeasurement</a>	13
2.7.3	<a href="#">Member Data Documentation</a>	13
2.7.3.1	<a href="#">AppliedCurrentVector</a>	13
2.7.3.2	<a href="#">Field</a>	13
2.7.3.3	<a href="#">Position</a>	13
2.8	<a href="#">MagneticState Struct Reference</a>	13
2.8.1	<a href="#">Detailed Description</a>	14
2.9	<a href="#">ElectromagnetCalibration::MagneticWorkSpace Struct Reference</a>	14
2.9.1	<a href="#">Member Data Documentation</a>	14
2.9.1.1	<a href="#">xMax</a>	14
2.9.1.2	<a href="#">xMin</a>	14
2.9.1.3	<a href="#">yMax</a>	14
2.9.1.4	<a href="#">yMin</a>	15
2.9.1.5	<a href="#">zMax</a>	15
2.9.1.6	<a href="#">zMin</a>	15
2.10	<a href="#">ScalarPotential Class Reference</a>	15
2.10.1	<a href="#">Detailed Description</a>	16
2.10.2	<a href="#">Constructor &amp; Destructor Documentation</a>	16
2.10.2.1	<a href="#">ScalarPotential</a>	16
2.10.3	<a href="#">Member Function Documentation</a>	17
2.10.3.1	<a href="#">getGradient</a>	17
2.10.3.2	<a href="#">getSourceStruct</a>	17
2.10.3.3	<a href="#">getState</a>	17
2.10.3.4	<a href="#">getValue</a>	17
2.10.3.5	<a href="#">packCalibrationState</a>	18
2.10.3.6	<a href="#">remapSecondDerivativeMat</a>	18
2.10.3.7	<a href="#">remapSecondDerivativeVec</a>	18
2.10.3.8	<a href="#">removeSourceStruct</a>	18
2.10.3.9	<a href="#">setSourceStruct</a>	18
2.11	<a href="#">ScalarPotentialCalibrationJacobians Struct Reference</a>	19
2.11.1	<a href="#">Constructor &amp; Destructor Documentation</a>	19

---

2.11.1.1	ScalarPotentialCalibrationJacobians	19
2.12	ScalarPotentialState Struct Reference	20
2.13	ScalarPotential::srcCoeff Struct Reference	20
2.14	ScalarPotential::srcStruct Class Reference	21
2.14.1	Detailed Description	21
2.14.2	Member Data Documentation	21
2.14.2.1	A_Coeff	21
2.14.2.2	B_Coeff	21
2.14.2.3	srcDirection	21
2.14.2.4	srcPosition	21
<b>Index</b>		<b>22</b>



# Chapter 1

## Class Index

### 1.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

<a href="#">YAML::convert&lt; Eigen::Matrix3d &gt;</a>	3
<a href="#">YAML::convert&lt; Eigen::MatrixXd &gt;</a>	3
<a href="#">YAML::convert&lt; Eigen::Vector3d &gt;</a>	3
<a href="#">YAML::convert&lt; Eigen::VectorXd &gt;</a>	4
<a href="#">YAML::convert&lt; std::vector&lt; double &gt; &gt;</a>	4
<a href="#">ElectromagnetCalibration</a>	
Class describing the calibration of an arbitrary magnetic system	4
<a href="#">MagneticMeasurement</a>	
The <a href="#">MagneticMeasurementData</a> struct provides the format calibration data must be supplied for the calibration	12
<a href="#">MagneticState</a>	
The <a href="#">MagneticState</a> struct contains information necessary to quantify the field at a position for control	13
<a href="#">ElectromagnetCalibration::MagneticWorkSpace</a>	14
<a href="#">ScalarPotential</a>	
Class describing the field of a collection of scalar potentials	15
<a href="#">ScalarPotentialCalibrationJacobians</a>	19
<a href="#">ScalarPotentialState</a>	20
<a href="#">ScalarPotential::srcCoeff</a>	20
<a href="#">ScalarPotential::srcStruct</a>	
The <a href="#">srcStruct</a> struct describes the scalar potential for an individual source	21





## Chapter 2

# Class Documentation

### 2.1 `YAML::convert< Eigen::Matrix3d >` Struct Template Reference

#### Static Public Member Functions

- static Node **encode** (const Eigen::Matrix3d &rhs)
- static bool **decode** (const Node &node, Eigen::Matrix3d &rhs)

The documentation for this struct was generated from the following file:

- EigenToYAML.h

### 2.2 `YAML::convert< Eigen::MatrixXd >` Struct Template Reference

#### Static Public Member Functions

- static Node **encode** (const Eigen::MatrixXd &rhs)
- static bool **decode** (const Node &node, Eigen::MatrixXd &rhs)

The documentation for this struct was generated from the following file:

- EigenToYAML.h

### 2.3 `YAML::convert< Eigen::Vector3d >` Struct Template Reference

#### Static Public Member Functions

- static Node **encode** (const Eigen::Vector3d &rhs)
- static bool **decode** (const Node &node, Eigen::Vector3d &rhs)

The documentation for this struct was generated from the following file:

- EigenToYAML.h

## 2.4 `YAML::convert< Eigen::VectorXd >` Struct Template Reference

### Static Public Member Functions

- static Node **encode** (const Eigen::VectorXd &rhs)
- static bool **decode** (const Node &node, Eigen::VectorXd &rhs)

The documentation for this struct was generated from the following file:

- EigenToYAML.h

## 2.5 `YAML::convert< std::vector< double > >` Struct Template Reference

### Static Public Member Functions

- static Node **encode** (const std::vector< double > &rhs)
- static bool **decode** (const Node &node, std::vector< double > &rhs)

The documentation for this struct was generated from the following file:

- EigenToYAML.h

## 2.6 ElectromagnetCalibration Class Reference

a class describing the calibration of an arbitrary magnetic system

```
#include <electromagnet_calibration.h>
```

### Classes

- struct [MagneticWorkSpace](#)

### Public Types

- enum [calibration\\_constraints](#) { [UNIT\\_HEADING\\_ONLY](#), [HEADING\\_AND\\_POSITION](#), [HEADING\\_THEN\\_POSITION](#) }

*The calibration\_constraints enum defines what constraints are active during calibration and how they are applied.*

### Public Member Functions

- [ElectromagnetCalibration](#) (std::string calibrationFileName)  
*constructor that builds a calibrated electromagnet system based on a preexisting yaml encoded calibration file.*
- [ElectromagnetCalibration](#) (std::string systemName, const [MagneticWorkSpace](#) &workSpace\_, const std::vector< [ScalarPotential](#) > &coilList, const [ScalarPotential](#) &dc\_field\_offset=[ScalarPotential](#)())  
*constructor that builds a calibrated electromagnet system based on a list of scalar potentials and an optional offset.*
- Eigen::Vector3d [fieldAtPoint](#) (const Eigen::VectorXd &currentVector, const Eigen::Vector3d &position=[Eigen::Vector3d::Zero](#)()) const  
*returns the field at a point*
- Eigen::Matrix3d [gradientAtPoint](#) (const Eigen::VectorXd &currentVector, const Eigen::Vector3d &position=[Eigen::Vector3d::Zero](#)()) const

- returns the 3x3 symetric gradient matrix at a desired location*

  - Vector8d [fieldAndGradientAtPoint](#) (const Eigen::VectorXd &currentVector, const Eigen::Vector3d &position=Eigen::Vector3d::Zero()) const

*returns the 8x1 stacked field over gradient vector*

  - Vector8d [offsetFieldAndGradientAtPoint](#) (const Eigen::Vector3d &position=Eigen::Vector3d::Zero()) const

*returns the 8x1 stacked field over gradient vector due to the zero-current field offset*

  - Eigen::MatrixXd [fieldCurrentJacobian](#) (const Eigen::Vector3d &position=Eigen::Vector3d::Zero()) const

*returns the 3xN matrix mapping field at a point to the current in each of the N sources*

  - Eigen::MatrixXd [gradientCurrentJacobian](#) (const Eigen::Vector3d &position=Eigen::Vector3d::Zero()) const

*returns the 5xN matrix mapping the field radiant at a point to the current in each of the N sources*

  - Eigen::MatrixXd [fieldAndGradientCurrentJacobian](#) (const Eigen::Vector3d &position=Eigen::Vector3d::Zero()) const

*returns the 8xN matrix mapping of the stacked field over field gradient at a point to the current in each of the N sources*

  - Eigen::Matrix< double, 5, 3 > [gradientPositionJacobian](#) (const Eigen::VectorXd &currentVector, const Eigen::Vector3d &position=Eigen::Vector3d::Zero()) const

*returns the 5x3 field gradient jacobian at a point given the currents in each of the N sources*

  - void [fullMagneticState](#) (Eigen::Vector3d &[fieldAtPoint](#), Eigen::Matrix< double, 8, 3 > &fieldGradientPositionJacobian, Eigen::MatrixXd &fieldGradientCurrentJacobian, const Eigen::VectorXd &current, const Eigen::Vector3d &position=Eigen::Vector3d::Zero()) const

*calculates the field, field and field gradient jacobians, and the current jacobians at a point given the currents in each of the N sources this faunction is more efficient than calling each of the applicable functions seporately.*

  - [MagneticState fullMagneticState](#) (const Eigen::VectorXd &currentVector, const Eigen::Vector3d &position=Eigen::Vector3d::Zero()) const

*calculates the field, field and field gradient jacobians, and the current jacobians at a point given the currents in each of the N sources this faunction is more efficient than calling each of the applicable functions seporately.*

  - bool [loadCalibration](#) (std::string fileName)

*loads a new calibration file*

  - bool [writeCalibration](#) (std::string fileName) const

*writes a new calibration file*

  - int [getNumberOfCoils](#) () const

*returns the number of coils in the calibration*

  - int [getNumberOfSources](#) (unsigned int coilNum) const

*returns the number of sources for the given coil*

  - int [getNumberOfCoeffients](#) (unsigned int coilNum, unsigned int srcNum) const

*returns the number of coefficients for the given source*

  - bool [hasOffset](#) () const

*returns if the calibration has a DC offset*

  - std::string [getName](#) () const

*returns the calibration name*

  - bool [pointInWorkspace](#) (const Eigen::Vector3d &position) const

*checks to see if a point lies within the calibrated workspace*

  - [MagneticWorkspace getWorkspace](#) () const

*getWorkspace returns the rectangular extent of the calibrated workspace*

  - void [setWorkspace](#) (const [MagneticWorkspace](#) &ws)

*sets the magnetic workspace to the desired specification*

  - void [useOffset](#) (bool offsetOn)

*enables or disables the use of the offset, if one exists.*

  - void [useOffset](#) (const [ScalarPotential](#) &newOffset)

*adds an offset to the system and enables it.*

  - bool [useOffset](#) () const

*returns if the offset is enabled or disabled.*

- void `calibrate` (std::string calibrationName, const std::vector< [MagneticMeasurement](#) > &dataList, bool printProgress=true, bool `printStats`=true, `calibration_constraints` constraint=HEADING\_THEN\_POSITION, double minimumSourceToCenterDistance=-1, double maximumSourceToCenterDistance=-1, double convergenceTolerance=1e-12, int maxIterations=10000, int numberOfConvergedIterations=1)  
*calibrate* Performs a system calibration based on gathered data and a current guess as to the scalar potential structure.
- void `printStats` (const std::vector< [MagneticMeasurement](#) > &dataList) const  
*Prints to the terminal (cout) statistics describing how well the system reproduces the magnetic measurements provided.*

## Static Public Member Functions

- static Eigen::Matrix3d `remapGradientVector` (const Vector5d &gradVector)  
*converts a 5x1 gradient vector into a symmetric zero trace 3x3 matrix*
- static Vector5d `remapGradientMatrix` (const Eigen::Matrix3d &gradMatrix)  
*converts a 3x3 gradient matrix into the 5x1 gradient vector*
- static Eigen::MatrixXd `packForceMatrix` (const Eigen::Vector3d &moment)  
*converts a 3x1 moment vector into a 3x5 force matrix*

## Protected Member Functions

- [ElectromagnetCalibration](#) ()
- bool `checkSourcePositions` (bool printWarning=false) const

## Protected Attributes

- [MagneticWorkSpace](#) `workSpace`
- std::vector< [ScalarPotential](#) > `coilList`
- [ScalarPotential](#) `offset`
- bool `use_offset`
- std::string `name`

### 2.6.1 Detailed Description

a class describing the calibration of an arbitrary magnetic system

This class assumes the system can be described by spherical harmonic scalar potentials at multiple locations with weightings proportional to the currents applied.

### 2.6.2 Member Enumeration Documentation

#### 2.6.2.1 enum `ElectromagnetCalibration::calibration_constraints`

The `calibration_constraints` enum defines what constraints are active during calibration and how they are applied.

#### Enumerator

**UNIT\_HEADING\_ONLY** Constrains the azimuth of the potentials to be unit length

**HEADING\_AND\_POSITION** Constrains the azimuth of potentials to be unit length and enforces that the positions lie in a spherical annulus outside of the measured data and prevents them from going to infinity.

**HEADING\_THEN\_POSITION** First solves with the heading constraints, then it resolves pushing any sources that lie inside the measurement data region out of a bounding circle of the data.

### 2.6.3 Constructor & Destructor Documentation

#### 2.6.3.1 ElectromagnetCalibration::ElectromagnetCalibration ( std::string *calibrationFileName* )

constructor that builds a calibrated electromagnet system based on a preexisting yaml encoded calibration file.

Parameters

<i>calibrationFileName</i>	is the file location for the calibration
----------------------------	--

#### 2.6.3.2 ElectromagnetCalibration::ElectromagnetCalibration ( std::string *systemName*, const MagneticWorkspace & *workspace\_*, const std::vector< ScalarPotential > & *coilList*, const ScalarPotential & *dc\_field\_offset* = ScalarPotential ( ) )

constructor that builds a calibrated electromagnet system based on a list of scalar potentials and an optional offset.

Parameters

<i>workspace_</i>	The workspace for which this calibration applies.
<i>coilList</i>	The list of coils and their respective sources.
<i>dc_field_offset</i>	The dc offset field, if any.

#### 2.6.3.3 ElectromagnetCalibration::ElectromagnetCalibration ( ) [protected]

Default Constructor only available to inheriting classes

### 2.6.4 Member Function Documentation

#### 2.6.4.1 void ElectromagnetCalibration::calibrate ( std::string *calibrationName*, const std::vector< MagneticMeasurement > & *dataList*, bool *printProgress* = true, bool *printStats* = true, calibration\_constraints *constraint* = HEADING\_THEN\_POSITION, double *minimumSourceToCenterDistance* = -1, double *maximumSourceToCenterDistance* = -1, double *convergenceTolerance* = 1e-12, int *maxIterations* = 10000, int *numberOfConvergedIterations* = 1 )

calibrate Performs a system calibration based on gathered data and a current guess as to the scalar potential structure.

Parameters

<i>calibrationName</i>	The name of the calibration.
<i>dataList</i>	The list of magnetic measurements.
<i>printProgress</i>	Boolean to identify if the convergence progress should be printed with cout.
<i>printStats</i>	Boolean to identify if the convergence statistics should be printed with cout once completed.
<i>constraint</i>	Identifies what kind of constraints should be applied to the positions and headings during convergence.
<i>minimumSourceToCenterDistance</i>	Identifies the minimum acceptable distance between the center of the workspace and any scalar potential source. Default is just outside workspace volume.
<i>maximumSourceToCenterDistance</i>	Identifies the maximum acceptable distance between the center of the workspace and any scalar potential source. Default is 10 times the initial guess distances.

<i>convergence-Tolerance</i>	Specifies the convergence tolerance. Default is 1e-12.
<i>maxIterations</i>	Specifies the maximum number of iterations to be used to prevent the loop from infinite cycles.
<i>numberOfConvergedIterations</i>	Specifies the number of sequential converged passes to prevent a false positive in convergence.

=0

**2.6.4.2** `Vector8d ElectromagnetCalibration::fieldAndGradientAtPoint ( const Eigen::VectorXd & currentVector, const Eigen::Vector3d & position = Eigen::Vector3d::Zero() ) const`

returns the 8x1 stacked field over gradient vector

Parameters

<i>currentVector</i>	is an ordered list of currents in each coil
<i>position</i>	is the position in the workspace the field is desired

The gradient matrix has been repacked, since it is symmetric and has zero trace, into a five element vector. The element order is:  $[dB_x/dx, dB_x/dy, dB_x/dz, dB_y/dy, dB_y/dz]^T$ . This function does not check to see if the point is actually in the calibrated workspace.

**2.6.4.3** `Eigen::MatrixXd ElectromagnetCalibration::fieldAndGradientCurrentJacobian ( const Eigen::Vector3d & position = Eigen::Vector3d::Zero() ) const`

returns the 8xN matrix mapping of the stacked field over field gradient at a point to the current in each of the N sources

Parameters

<i>position</i>	is the position in the workspace the field is desired
-----------------	---

The gradient matrix has been repacked, since it is symmetric and has zero trace, into a five element vector. The element order is:  $[dB_x/dx, dB_x/dy, dB_x/dz, dB_y/dy, dB_y/dz]^T$ . This function does not check to see if the point is actually in the calibrated workspace.

**2.6.4.4** `Eigen::Vector3d ElectromagnetCalibration::fieldAtPoint ( const Eigen::VectorXd & currentVector, const Eigen::Vector3d & position = Eigen::Vector3d::Zero() ) const`

returns the field at a point

Parameters

<i>currentVector</i>	is an ordered list of currents in each coil
<i>position</i>	is the position in the workspace the field is desired

This function does not check to see if the point is actually in the calibrated workspace.

**2.6.4.5** `Eigen::MatrixXd ElectromagnetCalibration::fieldCurrentJacobian ( const Eigen::Vector3d & position = Eigen::Vector3d::Zero() ) const`

returns the 3xN matrix mapping field at a point to the current in each of the N sources

Parameters

<i>position</i>	is the position in the workspace the field is desired
-----------------	---

This function does not check to see if the point is actually in the calibrated workspace.

```
2.6.4.6 void ElectromagnetCalibration::fullMagneticState ( Eigen::Vector3d & fieldAtPoint, Eigen::Matrix< double, 8, 3 > &  
    fieldGradientPositionJacobian, Eigen::MatrixXd & fieldGradientCurrentJacobian, const Eigen::VectorXd & current,  
    const Eigen::Vector3d & position = Eigen::Vector3d::Zero() ) const
```

calculates the field, field and field gradient jacobians, and the current jacobians at a point given the currents in each of the N sources this faunction is more efficient than calling each of the applicable functions separately.

## Parameters

<i>fieldAtPoint</i>	a pass by reference Vector to return the calculated field
<i>fieldGradient-PositionJacobian</i>	a pass by reference matrix to return the field jacobian stacked over the field gradient jacobian
<i>fieldGradient-CurrentJacobian</i>	a pass by reference matrix to return the field and gradient current jacobian
<i>currentVector</i>	is an orderd list of currents in each coil
<i>position</i>	is the position in the workspace the field is desired

The 3x3 gradient and 3x3x3 field gradient jacobian tensor has been repacked, since the 3x3 field gradient is symetric and has zero trace, into a 8x3 element vector. The element order is:

$$\begin{bmatrix} \frac{\partial B_x}{\partial x} & \frac{\partial B_x}{\partial y} & \frac{\partial B_x}{\partial z} \\ \frac{\partial B_x}{\partial y} & \frac{\partial B_y}{\partial y} & \frac{\partial B_y}{\partial z} \\ \frac{\partial B_x}{\partial z} & \frac{\partial B_y}{\partial z} & -\left(\frac{\partial B_x}{\partial x} + \frac{\partial B_y}{\partial y}\right) \\ \frac{\partial^2 B_x}{\partial x \partial x} & \frac{\partial^2 B_x}{\partial x \partial y} & \frac{\partial^2 B_x}{\partial x \partial z} \\ \frac{\partial^2 B_x}{\partial y \partial x} & \frac{\partial^2 B_x}{\partial y \partial y} & \frac{\partial^2 B_x}{\partial y \partial z} \\ \frac{\partial^2 B_x}{\partial z \partial x} & \frac{\partial^2 B_x}{\partial z \partial y} & \frac{\partial^2 B_x}{\partial z \partial z} \\ \frac{\partial^2 B_y}{\partial y \partial x} & \frac{\partial^2 B_y}{\partial y \partial y} & \frac{\partial^2 B_y}{\partial y \partial z} \\ \frac{\partial^2 B_y}{\partial z \partial x} & \frac{\partial^2 B_y}{\partial z \partial y} & \frac{\partial^2 B_y}{\partial z \partial z} \end{bmatrix}$$

This function does not check to see if the point is actually in the calibrated workspace.

**2.6.4.7 MagneticState ElectromagnetCalibration::fullMagneticState ( const Eigen::VectorXd & *currentVector*, const Eigen::Vector3d & *position* = Eigen::Vector3d::Zero() ) const**

calculates the field, field and field gradient jacobians, and the current jacobians at a point given the currents in each of the N sources this faunction is more efficient than calling each of the applicable functions separately.

## Parameters

<i>currentVector</i>	is an orderd list of currents in each coil
<i>position</i>	is the position in the workspace the field is desired

## Returns

the information on the magnetic field at a point in the form of a [MagneticState](#) object.

**2.6.4.8 Eigen::Matrix3d ElectromagnetCalibration::gradientAtPoint ( const Eigen::VectorXd & *currentVector*, const Eigen::Vector3d & *position* = Eigen::Vector3d::Zero() ) const**

returns the 3x3 symetric gradient matrix at a desired location

## Parameters

<i>currentVector</i>	is an orderd list of currents in each coil
<i>position</i>	is the position in the workspace the field is desired

This function does not check to see if the point is actually in the calibrated workspace.

**2.6.4.9 Eigen::MatrixXd ElectromagnetCalibration::gradientCurrentJacobian ( const Eigen::Vector3d & *position* = Eigen::Vector3d::Zero() ) const**

returns the 5xN matrix mapping the field radiant at a point to the current in each of the N sources



## Parameters

<i>position</i>	is the position in the workspace the field is desired
-----------------	---

The gradient matrix has been repacked, since it is symmetric and has zero trace, into a five element vector. The element order is:  $[dBx/dx, dBx/dy, dBx/dz, dBy/dy, dBy/dz]^T$ . This function does not check to see if the point is actually in the calibrated workspace.

**2.6.4.10** `Eigen::Matrix< double, 5, 3 > ElectromagnetCalibration::gradientPositionJacobian ( const Eigen::VectorXd & currentVector, const Eigen::Vector3d & position = Eigen::Vector3d::Zero() ) const`

returns the 5x3 field gradient jacobian at a point given the currents in each of the N sources

## Parameters

<i>currentVector</i>	is an ordered list of currents in each coil
<i>position</i>	is the position in the workspace the field is desired

The 3x3x3 tensor has been repacked, since the 3x3 field gradient is symmetric and has zero trace, into a 5x3 element vector. The element order is:  $[dBx/dxdx, dBx/dxdy, dBx/dxdz, dBx/dydx, dBx/dydy, dBx/dydz, dBx/dzdx, dBx/dzdy, dBx/dzdz, dBy/dydx, dBy/dydy, dBy/dydz, dBy/dzdx, dBy/dzdy, dBy/dzdz]$ . This function does not check to see if the point is actually in the calibrated workspace.

**2.6.4.11** `bool ElectromagnetCalibration::loadCalibration ( std::string fileName )`

loads a new calibration file

## Parameters

<i>a</i>	string pointing to the location of the yaml formatted calibration file
----------	--

**2.6.4.12** `Vector8d ElectromagnetCalibration::offsetFieldAndGradientAtPoint ( const Eigen::Vector3d & position = Eigen::Vector3d::Zero() ) const`

returns the 8x1 stacked field over gradient vector due to the zero-current field offset

## Parameters

<i>position</i>	is the position in the workspace the field is desired
-----------------	---

The gradient matrix has been repacked, since it is symmetric and has zero trace, into a five element vector. The element order is:  $[dBx/dx, dBx/dy, dBx/dz, dBy/dy, dBy/dz]^T$ . This function does not check to see if the point is actually in the calibrated workspace.

**2.6.4.13** `Eigen::MatrixXd ElectromagnetCalibration::packForceMatrix ( const Eigen::Vector3d & moment ) [static]`

converts a 3x1 moment vector into a 3x5 force matrix

## Parameters

<i>moment</i>	is the magnetic moment that is packed into the force matrix
---------------	---

converts a 3x1 moment vector into a 3x5 force matrix to allow easy calculation of the magnetic force by multiplication with the gradient vector

**2.6.4.14** `bool ElectromagnetCalibration::pointInWorkspace ( const Eigen::Vector3d & position ) const`

checks to see if a point lies within the calibrated workspace

## Parameters

<i>position</i>	the desired position to check
-----------------	-------------------------------

**2.6.4.15** `void ElectromagnetCalibration::printStats ( const std::vector< MagneticMeasurement > & dataList ) const`

Prints to the terminal (cout) statistics describing how well the system reproduces the magnetic measurements provided.

## Parameters

<i>dataList</i>	A set of magnetic measurements to compare the calibration to.
-----------------	---

The output of this function provides the  $R^2$  value, the mean error, and the square root of covariance (standard deviation) of the error in both a millitesla and normalized percentage basis.

**2.6.4.16** `Vector5d ElectromagnetCalibration::remapGradientMatrix ( const Eigen::Matrix3d & gradMatrix ) [static]`

converts a 3x3 gradient matrix into the 5x1 gradient vector

## Parameters

<i>gradMatrix</i>	is the desired matrix to be remapped
-------------------	--------------------------------------

This function does not check to verify the matrix is indeed symmetric and zero trace

**2.6.4.17** `Eigen::Matrix3d ElectromagnetCalibration::remapGradientVector ( const Vector5d & gradVector ) [static]`

converts a 5x1 gradient vector into a symmetric zero trace 3x3 matrix

## Parameters

<i>gradVector</i>	is the desired vector to be remapped
-------------------	--------------------------------------

**2.6.4.18** `bool ElectromagnetCalibration::writeCalibration ( std::string fileName ) const`

writes a new calibration file

## Parameters

<i>a</i>	string pointing to the location for the yaml formatted calibration file
----------	---

The documentation for this class was generated from the following files:

- `electromagnet_calibration.h`
- `electromagnet_calibration.cpp`

## 2.7 MagneticMeasurement Struct Reference

The `MagneticMeasurementData` struct provides the format calibration data must be supplied for the calibration.

```
#include <electromagnet_calibration.h>
```

### Public Member Functions

- [MagneticMeasurement](#) ()
- [MagneticMeasurement](#) (const Eigen::Vector3d &[Field](#), const Eigen::Vector3d &[Pos](#), const Eigen::VectorXd &[CurrentVec](#))

*calibrationDataPoint*

## Public Attributes

- Eigen::Vector3d [Field](#)
- Eigen::Vector3d [Position](#)
- Eigen::VectorXd [AppliedCurrentVector](#)

### 2.7.1 Detailed Description

The MagneticMeasurementData struct provides the format calibration data must be supplied for the calibration.

### 2.7.2 Constructor & Destructor Documentation

#### 2.7.2.1 MagneticMeasurement::MagneticMeasurement ( )

Initializes all parameters to zero.

#### 2.7.2.2 MagneticMeasurement::MagneticMeasurement ( const Eigen::Vector3d & *Field*, const Eigen::Vector3d & *Pos*, const Eigen::VectorXd & *CurrentVec* )

*calibrationDataPoint*

Parameters

<i>Field</i>	the field value in Tesla
<i>Pos</i>	the position of the measurement in meters
<i>CurrentVec</i>	the applied current vector in Amps

### 2.7.3 Member Data Documentation

#### 2.7.3.1 Eigen::VectorXd MagneticMeasurement::AppliedCurrentVector

The applied current vector in Amps. A Nx1 Vector

#### 2.7.3.2 Eigen::Vector3d MagneticMeasurement::Field

The measured Field in Tesla. A 3x1 Vector

#### 2.7.3.3 Eigen::Vector3d MagneticMeasurement::Position

The position of the measurement in meters. A 3x1 Vector

The documentation for this struct was generated from the following files:

- `electromagnet_calibration.h`
- `electromagnet_calibration.cpp`

## 2.8 MagneticState Struct Reference

The [MagneticState](#) struct contains information necessary to quantify the field at a position for control.

```
#include <electromagnet_calibration.h>
```

## Public Attributes

- Eigen::Vector3d [Field](#)  
*Field* The magnetic field at the position in Tesla. This is a 3x1 Matrix.
- Eigen::Matrix3d [Gradient](#)  
*Gradient* The Magnetic gradient at the position in Tesla/Meter. This is a 3x3 Matrix.
- Eigen::Matrix< double, 5, 3 > [GradientPositionJacobian](#)  
*GradientPositionJacobian* The rate of change of the 5 unique gradient terms with respect to position in Tesla/Meter<sup>2</sup>. This is a 5x3 Matrix, to get the 3x3x3 Gradient derivative tensor, the function [ElectromagnetCalibration::remapGradientVector](#) can be used on each column to get the gradient matrix change in x,y and z in that order.
- Eigen::MatrixXd [FieldGradientActuationMatrix](#)  
*FieldGradientActuationMatrix* The field and gradient (packed into a 5x1 vector) current jacobian. This is a 8xN matrix, where N is the number of current sources. The first 3 rows are for field the last five rows are for gradient [ElectromagnetCalibration::remapGradientVector](#).

### 2.8.1 Detailed Description

The [MagneticState](#) struct contains information necessary to quantify the field at a position for control.

The documentation for this struct was generated from the following file:

- `electromagnet_calibration.h`

## 2.9 ElectromagnetCalibration::MagneticWorkspace Struct Reference

### Public Member Functions

- **MagneticWorkspace** (double size)
- **MagneticWorkspace** (double [xMin](#), double [xMax](#), double [yMin](#), double [yMax](#), double [zMin](#), double [zMax](#))

### Public Attributes

- double [xMin](#)
- double [xMax](#)
- double [yMin](#)
- double [yMax](#)
- double [zMin](#)
- double [zMax](#)

### 2.9.1 Member Data Documentation

#### 2.9.1.1 double ElectromagnetCalibration::MagneticWorkspace::xMax

Maximum X position in Meters

#### 2.9.1.2 double ElectromagnetCalibration::MagneticWorkspace::xMin

Minimum X Position in Meters

#### 2.9.1.3 double ElectromagnetCalibration::MagneticWorkspace::yMax

Maximum Y Position in Meters

## 2.9.1.4 double ElectromagnetCalibration::MagneticWorkSpace::yMin

Minimum Y Position in Meters

## 2.9.1.5 double ElectromagnetCalibration::MagneticWorkSpace::zMax

Maximum Z Position in Meters

## 2.9.1.6 double ElectromagnetCalibration::MagneticWorkSpace::zMin

Minimum Z Position in Meters

The documentation for this struct was generated from the following files:

- `electromagnet_calibration.h`
- `electromagnet_calibration.cpp`

## 2.10 ScalarPotential Class Reference

a class describing the field of a collection of scalar potentials

```
#include <scalarPotential.h>
```

### Classes

- struct [srcCoeff](#)
- class [srcStruct](#)

The [srcStruct](#) struct describes the scalar potential for an individual source.

### Public Member Functions

- [ScalarPotential](#) ()  
*ScalarPotential initializes an empty scalar potential, one with no sources.*
- [ScalarPotential](#) (const std::vector< [srcStruct](#) > &srcList)  
*the constructor from a coil list.*
- [ScalarPotentialState](#) [getState](#) (const Eigen::Vector3d &position, int sourceNumber=-1) const  
*getState returns the state at the position requested*
- double [getValue](#) (const Eigen::Vector3d &position, int sourceNumber=-1) const  
*getValue Returns the scalar potential magnitude at the position requested*
- Eigen::Vector3d [getGradient](#) (const Eigen::Vector3d &position, int sourceNumber=-1) const  
*getGradient Returns the spacial gradient of the potential at the position requested*
- unsigned int [getNumberOfSources](#) () const  
*returns the number of sources for the given coil*
- [srcStruct](#) [getSourceStruct](#) (unsigned int sourceNumber) const  
*getSourceStruct returns a copy of the source structure*
- void [setSourceStruct](#) (unsigned int sourceNumber, const [srcStruct](#) &newSrc)  
*setSourceStruct Sets a new source to replace an existing source. Good to use with*
- void [removeSourceStruct](#) (unsigned int sourceNumber)  
*removeSourceStruct Removes a source from the list of sources.*

## Static Public Member Functions

- static Eigen::Matrix3d [remapSecondDerivativeVec](#) (const Vector5d &gradVector)  
*converts a 5x1 gradient vector into a symmetric zero trace 3x3 matrix*
- static Vector5d [remapSecondDerivativeMat](#) (const Eigen::Matrix3d &gradMatrix)  
*converts a 3x3 gradient matrix into the 5x1 gradient vector*

## Protected Member Functions

- [ScalarPotentialCalibrationJacobians](#) **srcCalibrationInformation** (const Eigen::Vector3d &position, unsigned int srcNum) const
- template<typename Derived >  
void [packCalibrationState](#) (Eigen::MatrixBase< Derived > const &stateVector\_) const
- template<typename Derived >  
void **unpackCalibrationState** (Eigen::MatrixBase< Derived > const &stateVector\_)
- template<typename Derived , typename Derived2 >  
void **packJacobians** (int srcNum, double current, const Eigen::Vector3d &pos, const Eigen::Vector3d &fieldError, Eigen::MatrixBase< Derived > const &firstTransposed\_, Eigen::MatrixBase< Derived2 > const &hessian\_)
- int **getNumCalibrationParameters** (int srcNum=-1) const

## Static Protected Member Functions

- static double [LegendrePolynomial](#) (double x, int order, int der=0)  
*Calculates the Legendre Polynomial of a given order derivative  $X \leq (-1, 1)$*
- static void **srcFieldGradient** (const Eigen::Vector3d &position, const [srcStruct](#) &src, [ScalarPotentialState](#) &currentState)

## Protected Attributes

- std::vector< [srcStruct](#) > **srcList**
- int **numCalParameters**

## Friends

- class **ElectromagnetCalibration**

### 2.10.1 Detailed Description

a class describing the field of a collection of scalar potentials

This class assumes the system can be described by spherical harmonic scalar potentials at multiple locations. See. "PUBLICATION HERE"

### 2.10.2 Constructor & Destructor Documentation

#### 2.10.2.1 [ScalarPotential::ScalarPotential](#) ( const std::vector< [srcStruct](#) > & *srcList* )

the constructor from a coil list.

## Parameters

<i>coilList</i>	The list of coils and their respective sources.
<i>dc_field_offset</i>	The dc offset field, if any.

## 2.10.3 Member Function Documentation

2.10.3.1 Eigen::Vector3d ScalarPotential::getGradient ( const Eigen::Vector3d & *position*, int *sourceNumber* = -1 ) const

getGradient Returns the spacial gradient of the potential at the position requested

## Parameters

<i>position</i>	3D position of interest
<i>sourceNumber</i>	The contribution limited to a specific source. Default is -1, which is interperated as the total effect of all sources

## Returns

The value of the scalar potential spatial gradeint

2.10.3.2 ScalarPotential::srcStruct ScalarPotential::getSourceStruct ( unsigned int *sourceNumber* ) const

getSourceStruct returns a copy of the source structure

## Parameters

<i>sourceNumber</i>	The ordered number of the source to be copied.
---------------------	--

## Returns

## See Also

[srcStruct](#). If the number is out of bounds it will return an empty source.

2.10.3.3 ScalarPotentialState ScalarPotential::getState ( const Eigen::Vector3d & *position*, int *sourceNumber* = -1 ) const

getState returns the state at the position requested

## Parameters

<i>position</i>	3D position of interest
<i>sourceNumber</i>	The contribion limited to a specific source. Default is -1, which is interperated as the total effect all sources

## Returns

The Scalar Potential State

## See Also

[ScalarPotentialState](#)

2.10.3.4 double ScalarPotential::getValue ( const Eigen::Vector3d & *position*, int *sourceNumber* = -1 ) const

getValue Returns the scalar potential magnitude at the position requested

## Parameters

<i>position</i>	3D position of interest
<i>sourceNumber</i>	The contribution limited to a specific source. Default is -1, which is interpreted as the total effect of all sources

## Returns

The value of the scalar potential state

**2.10.3.5** `template<typename Derived > void ScalarPotential::packCalibrationState ( Eigen::MatrixBase< Derived > const & stateVector_ ) const` `[inline]`, `[protected]`

< Returns the vector packing of the node state

**2.10.3.6** `Vector5d ScalarPotential::remapSecondDerivativeMat ( const Eigen::Matrix3d & gradMatrix )` `[static]`

converts a 3x3 gradient matrix into the 5x1 gradient vector

## Parameters

<i>gradMatrix</i>	is the desired matrix to be remapped
-------------------	--------------------------------------

This function does not check to verify the matrix is indeed symmetric and zero trace

**2.10.3.7** `Eigen::Matrix3d ScalarPotential::remapSecondDerivativeVec ( const Vector5d & gradVector )` `[static]`

converts a 5x1 gradient vector into a symmetric zero trace 3x3 matrix

## Parameters

<i>gradVector</i>	is the desired vector to be remapped
-------------------	--------------------------------------

**2.10.3.8** `void ScalarPotential::removeSourceStruct ( unsigned int sourceNumber )`

`removeSourceStruct` Removes a source from the list of sources.

## Parameters

<i>sourceNumber</i>	The ordered number of the source to replace.
---------------------	--

**2.10.3.9** `void ScalarPotential::setSourceStruct ( unsigned int sourceNumber, const srcStruct & newSrc )`

`setSourceStruct` Sets a new source to replace an existing source. Good to use with

## See Also

[getSourceStruct](#) for modifying a source configuration.

## Parameters

<i>sourceNumber</i>	The ordered number of the source to replace.
---------------------	--



<code>newSrc</code>	The new source definition.
---------------------	----------------------------

This function will add empty sources until sourceNumber is reached if sourceNumber is greater than the current number of sources.

The documentation for this class was generated from the following files:

- scalarPotential.h
- scalarPotential.cpp

## 2.11 ScalarPotentialCalibrationJacobians Struct Reference

### Public Member Functions

- [ScalarPotentialCalibrationJacobians](#) ()

### Public Attributes

- Eigen::Vector3d [firstSpatialDerivative](#)  
*Field, the gradient of the potential.*
- Eigen::MatrixXd [firstSpatialDerivative\\_A\\_CoeffDerivative](#)  
*How the field changes with the A coefficients.*
- Eigen::MatrixXd [firstSpatialDerivative\\_B\\_CoeffDerivative](#)  
*How the field changes with the B coefficients.*
- Eigen::MatrixXd [firstSpatialDerivative\\_dA\\_dHeading](#)  
*The second derivate of the field with respect to the A coefficients and with Heading.*
- Eigen::MatrixXd [firstSpatialDerivative\\_dB\\_dHeading](#)  
*The second derivate of the field with respect to the B coefficients and with Heading.*
- Eigen::MatrixXd [firstSpatialDerivative\\_dA\\_dPosition](#)  
*The second derivate of the field with respect to the A coefficients and with Position.*
- Eigen::MatrixXd [firstSpatialDerivative\\_dB\\_dPosition](#)  
*The second derivate of the field with respect to the B coefficients and with Position.*
- Eigen::Matrix3d [firstSpatialDerivative\\_SourcePositionDerivative](#)  
*Field spatial gradient.*
- Eigen::Matrix3d [firstSpatialDerivative\\_SourceHeadingDerivative](#)  
*How the field changes with the source heading.*
- Eigen::Matrix< double, 5, 3 > [secondSpatialDerivative\\_SourcePositionDerivative](#)  
*5x3 matrix describing how the field spatial gradient changes with the source position*
- Eigen::Matrix< double, 5, 3 > [secondSpatialDerivative\\_SourceHeadingDerivative](#)  
*5x3 matrix describing how the field spatial gradient changes with the source heading*
- Eigen::Matrix< double, 9, 3 > [firstSpatialDerivative\\_secondSourceHeadingDerivative](#)  
*A list of 9x3 matrices describing how the field changes with the source heading  $[d(B*X)/dz; d(B*Y)/dz; d(B*Z)/dz]$ .*

### 2.11.1 Constructor & Destructor Documentation

#### 2.11.1.1 ScalarPotentialCalibrationJacobians::ScalarPotentialCalibrationJacobians ( )

< Field, the gradient of the potential.

< How the field changes with the A coefficients

< How the field changes with the B coefficients

- < Field spatial gradient
- < How the field changes with the source heading
- < the second deritive of field with heading ( $d(BX)/dz$ ;  $d(BY)/dz$ ;  $d(BZ)/dz$ )

The documentation for this struct was generated from the following files:

- scalarPotential.h
- scalarPotential.cpp

## 2.12 ScalarPotentialState Struct Reference

### Public Attributes

- double **value**  
*The value of the scalar potential.*
- Eigen::Vector3d **firstSpatialDerivative**  
*Field, the gradient of the potential.*
- Eigen::Matrix< double, 3, 3 > **secondSpatialDerivative**  
*Field spatial gradient.*
- Eigen::Matrix< double, 5, 3 > **thirdSpatialDerivative**  
*How the field spatial gradient changes with position, assumes potentials of order > 1. (no sources or sinks)*
- std::vector< Eigen::MatrixXd > **firstSpatialDerivative\_SourceHeadingDerivative**  
*A list of 3x3 matrices describing how the field changes with the source heading.*
- std::vector< Eigen::MatrixXd > **firstSpatialDerivative\_SourcePositionDerivative**  
*A list of 3x3 matrices describing how the field changes with the source position.*
- std::vector< Eigen::MatrixXd > **secondSpatialDerivative\_SourcePositionDerivative**  
*A list of 5x3 matrices describing how the field spatial gradient changes with the source position.*
- std::vector< Eigen::MatrixXd > **secondSpatialDerivative\_SourceHeadingDerivative**  
*A list of 5x3 matrices describing how the field spatial gradient changes with the source heading.*

The documentation for this struct was generated from the following files:

- scalarPotential.h
- scalarPotential.cpp

## 2.13 ScalarPotential::srcCoeff Struct Reference

### Public Member Functions

- **srcCoeff** (double value, unsigned int order)

### Public Attributes

- unsigned int **order**
- double **coeff**

The documentation for this struct was generated from the following files:

- scalarPotential.h
- scalarPotential.cpp

## 2.14 ScalarPotential::srcStruct Class Reference

The `srcStruct` struct describes the scalar potential for an individual source.

```
#include <scalarPotential.h>
```

### Public Member Functions

- unsigned int `getMaxOrder_A_Coeff` () const
- unsigned int `getMaxOrder_B_Coeff` () const

### Public Attributes

- `std::vector< srcCoeff > A_Coeff`
- `std::vector< srcCoeff > B_Coeff`
- `Eigen::Vector3d srcPosition`
- `Eigen::Vector3d srcDirection`

### 2.14.1 Detailed Description

The `srcStruct` struct describes the scalar potential for an individual source.

The field given by a sources is the negative gradient of a scalar potential PHI according to the equation:  $PHI = \sum (A\_coeff(n) * r^n + B\_coeff(n) * r^{(-n-1)}) * P\_n(\cos(\theta))$ ,  $n = 1..inf$  where  $r$  is the distance from the point of interest to the source position.  $\cos(\theta)$  is the angle between the  $r$  vector and the source direction.  $P\_n$  is a legendre polynomial of order  $n$ .  $A\_coeff$  and  $B\_Coeff$  define the contributions of each field shape. Here we only keep the first terms in the summation. Note: the length of  $A\_Coeff$  and  $B\_Coeff$  need not be the same.

### 2.14.2 Member Data Documentation

#### 2.14.2.1 `std::vector<srcCoeff> ScalarPotential::srcStruct::A_Coeff`

Ordered coefficients each associated with distances to an increasing positive power.

#### 2.14.2.2 `std::vector<srcCoeff> ScalarPotential::srcStruct::B_Coeff`

Ordered coefficients each associated with distances to an increasing negative power.

#### 2.14.2.3 `Eigen::Vector3d ScalarPotential::srcStruct::srcDirection`

Source Heading. Should be a unit vector

#### 2.14.2.4 `Eigen::Vector3d ScalarPotential::srcStruct::srcPosition`

Source Position in meters

The documentation for this class was generated from the following files:

- `scalarPotential.h`
- `scalarPotential.cpp`

# Index

- A\_Coeff
  - ScalarPotential::srcStruct, [21](#)
- AppliedCurrentVector
  - MagneticMeasurement, [13](#)
- B\_Coeff
  - ScalarPotential::srcStruct, [21](#)
- calibrate
  - ElectromagnetCalibration, [7](#)
- calibration\_constraints
  - ElectromagnetCalibration, [6](#)
- ElectromagnetCalibration
  - HEADING\_AND\_POSITION, [6](#)
  - HEADING\_THEN\_POSITION, [6](#)
  - UNIT\_HEADING\_ONLY, [6](#)
- ElectromagnetCalibration, [4](#)
  - calibrate, [7](#)
  - calibration\_constraints, [6](#)
  - ElectromagnetCalibration, [7](#)
  - ElectromagnetCalibration, [7](#)
  - fieldAndGradientAtPoint, [8](#)
  - fieldAndGradientCurrentJacobian, [8](#)
  - fieldAtPoint, [8](#)
  - fieldCurrentJacobian, [8](#)
  - fullMagneticState, [8](#), [10](#)
  - gradientAtPoint, [10](#)
  - gradientCurrentJacobian, [10](#)
  - gradientPositionJacobian, [11](#)
  - loadCalibration, [11](#)
  - offsetFieldAndGradientAtPoint, [11](#)
  - packForceMatrix, [11](#)
  - pointInWorkspace, [11](#)
  - printStats, [12](#)
  - remapGradientMatrix, [12](#)
  - remapGradientVector, [12](#)
  - writeCalibration, [12](#)
- ElectromagnetCalibration::MagneticWorkSpace, [14](#)
  - xMax, [14](#)
  - xMin, [14](#)
  - yMax, [14](#)
  - yMin, [14](#)
  - zMax, [15](#)
  - zMin, [15](#)
- Field
  - MagneticMeasurement, [13](#)
- fieldAndGradientAtPoint
  - ElectromagnetCalibration, [8](#)
- fieldAndGradientCurrentJacobian
  - ElectromagnetCalibration, [8](#)
- fieldAtPoint
  - ElectromagnetCalibration, [8](#)
- fieldCurrentJacobian
  - ElectromagnetCalibration, [8](#)
- fullMagneticState
  - ElectromagnetCalibration, [8](#), [10](#)
- getGradient
  - ScalarPotential, [17](#)
- getSourceStruct
  - ScalarPotential, [17](#)
- getState
  - ScalarPotential, [17](#)
- getValue
  - ScalarPotential, [17](#)
- gradientAtPoint
  - ElectromagnetCalibration, [10](#)
- gradientCurrentJacobian
  - ElectromagnetCalibration, [10](#)
- gradientPositionJacobian
  - ElectromagnetCalibration, [11](#)
- HEADING\_AND\_POSITION
  - ElectromagnetCalibration, [6](#)
- HEADING\_THEN\_POSITION
  - ElectromagnetCalibration, [6](#)
- loadCalibration
  - ElectromagnetCalibration, [11](#)
- MagneticMeasurement, [12](#)
  - AppliedCurrentVector, [13](#)
  - Field, [13](#)
  - MagneticMeasurement, [13](#)
  - MagneticMeasurement, [13](#)
  - Position, [13](#)
- MagneticState, [13](#)
- offsetFieldAndGradientAtPoint
  - ElectromagnetCalibration, [11](#)
- packCalibrationState
  - ScalarPotential, [18](#)
- packForceMatrix
  - ElectromagnetCalibration, [11](#)
- pointInWorkspace
  - ElectromagnetCalibration, [11](#)
- Position
  - MagneticMeasurement, [13](#)

printStats  
     ElectromagnetCalibration, 12

remapGradientMatrix  
     ElectromagnetCalibration, 12

remapGradientVector  
     ElectromagnetCalibration, 12

remapSecondDerivativeMat  
     ScalarPotential, 18

remapSecondDerivativeVec  
     ScalarPotential, 18

removeSourceStruct  
     ScalarPotential, 18

ScalarPotential, 15  
     getGradient, 17  
     getSourceStruct, 17  
     getState, 17  
     getValue, 17  
     packCalibrationState, 18  
     remapSecondDerivativeMat, 18  
     remapSecondDerivativeVec, 18  
     removeSourceStruct, 18  
     ScalarPotential, 16  
     ScalarPotential, 16  
     setSourceStruct, 18

ScalarPotential::srcCoeff, 20

ScalarPotential::srcStruct, 21  
     A\_Coeff, 21  
     B\_Coeff, 21  
     srcDirection, 21  
     srcPosition, 21

ScalarPotentialCalibrationJacobians, 19  
     ScalarPotentialCalibrationJacobians, 19  
     ScalarPotentialCalibrationJacobians, 19

ScalarPotentialState, 20

setSourceStruct  
     ScalarPotential, 18

srcDirection  
     ScalarPotential::srcStruct, 21

srcPosition  
     ScalarPotential::srcStruct, 21

UNIT\_HEADING\_ONLY  
     ElectromagnetCalibration, 6

writeCalibration  
     ElectromagnetCalibration, 12

xMax  
     ElectromagnetCalibration::MagneticWorkSpace,  
     14

xMin  
     ElectromagnetCalibration::MagneticWorkSpace,  
     14

YAML::convert< Eigen::Matrix3d >, 3  
 YAML::convert< Eigen::MatrixXd >, 3  
 YAML::convert< Eigen::Vector3d >, 3  
 YAML::convert< Eigen::VectorXd >, 4

YAML::convert< std::vector< double > >, 4

yMax  
     ElectromagnetCalibration::MagneticWorkSpace,  
     14

yMin  
     ElectromagnetCalibration::MagneticWorkSpace,  
     14

zMax  
     ElectromagnetCalibration::MagneticWorkSpace,  
     15

zMin  
     ElectromagnetCalibration::MagneticWorkSpace,  
     15